XL1-Blue MR Supercompetent Cells

Catalog #200229

MATERIALS PROVIDED

Materials provided	Quantity	Efficiency (cfu/μg of pUC18 DNA)
XL1-Blue MR supercompetent cells (colorless tubes)	5 imes 0.2 ml	$\geq 1 \times 10^{9}$
pUC18 control plasmid (0.1 ng/µl in TE buffer)	10 μl	
β-Mercaptoethanol (1.42 M)	25 μl	_

Storage: Supercompetent cells must be placed immediately at the bottom of a -80°C freezer directly from the dry ice shipping container. Do not store the cells in liquid nitrogen.

QUALITY CONTROL TESTING

Transformations are performed both with and without plasmid DNA using 100- μ l aliquots of cells and 100 pg of pUC18 control plasmid following the protocol outlined below. Following transformation, 2.5- μ l samples of the culture are plated in duplicate on LB agar plates with 100 μ g/ml of ampicillin. The plates are incubated at 37°C overnight and the efficiency is calculated based on the average number of colonies per plate.

BACKGROUND

XL1-Blue MR Genotype: $\Delta(mcrA)183 \Delta(mcrCB-hsdSMR-mrr)173$ endA1 supE44 thi-1 recA1 gyrA96 relA1 lac. (Genes listed signify mutant alleles.)

The XL1-Blue MR (Minus Restriction) strain is a restriction minus (McrA⁻, McrCB⁻, McrF⁻, Mrr⁻, HsdR⁻) derivative of Stratagene's XL1-Blue strain and is useful for cosmid-based cloning. XL1-Blue MR cells are deficient in all known restriction systems [$\Delta(mcrA)183$, $\Delta(mcrCB-hsdSMR-mrr)173$], and are endonuclease (*endA*), and recombination (*recA*) deficient. The *hsdR* mutation prevents the cleavage of cloned DNA by the *Eco*K endonuclease system, and the *recA* mutation helps ensure insert stability. The *endA* mutation greatly improves the quality of miniprep DNA.

Note Unlike the XL1-Blue strain, the XL1-Blue MR strain does not contain an F´episome and **does not support blue-white color** screening applications.

TRANSFORMATION PROTOCOL

- 1. Pre-chill two 14-ml BD Falcon polypropylene round-bottom tubes on ice. (One tube is for the experimental transformation and one tube is for the pUC18 control.) Preheat SOC medium[§] to 42°C.
- 2. Thaw the supercompetent cells on ice. When thawed, gently mix and aliquot 100 µl of cells into each of the two pre-chilled tubes.
- 3. Add 1.7 μ l of β -mercaptoethanol provided with this kit to each aliquot of cells.
- 4. Swirl the contents of the tubes gently. Incubate the cells on ice for 10 minutes, swirling gently every 2 minutes.
- 5. Add 0.1–50 ng of the experimental DNA (see *Quantity and Volume of DNA*, reverse page, for guidelines) to one aliquot of cells and add 1 µl of the pUC18 control DNA to the other aliquot. Swirl the tubes gently.
- 6. Incubate the tubes on ice for 30 minutes.
- 7. Heat-pulse the tubes in a 42° C water bath for 45 seconds. The duration of the heat pulse is **critical** for maximum efficiency.
- 8. Incubate the tubes on ice for 2 minutes.
- 9. Add 0.9 ml of preheated SOC medium and incubate the tubes at 37°C for 1 hour with shaking at 225–250 rpm.
- 10. Plate ≤200 µl of the transformation mixture on LB agar plates containing the appropriate antibiotic. For the pUC18 control transformation, plate 2.5 µl of the transformation on LB–ampicillin agar plates.[§]

Notes Cells may be concentrated by centrifuging at 1000 rpm for 10 minutes. Resuspend the pellet in 200 µl of SOC medium.

If plating <100 μ l of cells, pipet the cells into a 200 μ l pool of SOC medium and then spread the mixture with a sterile spreader. If plating \geq 100 μ l, the cells can be spread on the plates directly. Tilt and tap the spreader to remove the last drop of cells.

- 11. Incubate the plates at 37°C overnight.
- 12. For the pUC18 control, expect 250 colonies ($\ge 1 \times 10^9$ cfu/µg pUC18 DNA). For the experimental DNA, the number of colonies will vary according to the size and form of the transforming DNA, with larger and non-supercoiled DNA producing fewer colonies.

§See Preparation of Media and Reagents.

TRANSFORMATION GUIDELINES AND TROUBLESHOOTING

Storage Conditions: Competent and supercompetent cells are very sensitive to even small variations in temperature and must be stored at the bottom of a -80° C freezer. Transferring tubes from one freezer to another may result in a loss of efficiency.

Use of 14-ml BD Falcon polypropylene round-bottom tubes: It is important that 14-ml BD Falcon polypropylene round-bottom tubes (BD Biosciences Catalog #352059) are used for the transformation protocol, since other tubes may be degraded by β -mercaptoethanol. In addition, the duration of the heat-pulse is critical and has been optimized for these tubes.

Aliquoting Cells: Keep the cells on ice at all times during aliquoting. It is essential that the polypropylene tubes are placed on ice before the cells are thawed and that the cells are aliquoted directly into pre-chilled tubes. It is also important to use the volume of cells indicated in step 2 of the *Transformation Protocol*. Decreasing the volume will result in lower efficiencies.

Use of β -Mercaptoethanol (β -ME): β -ME has been shown to increase transformation efficiency. The β -ME provided is diluted and ready to use. A fresh 1:10 dilution (from a 14.2 M stock) may be used; however, Stratagene cannot guarantee results with β -ME from other sources.

Quantity and Volume of DNA: The greatest efficiency is obtained from the transformation of 1 μ l of 0.1 ng/ μ l supercoiled pUC18 DNA per reaction. A greater number of colonies may be obtained by transforming up to 50 ng DNA, although the resulting efficiency (cfu/ μ g DNA) may be lower. The volume of the DNA solution added to the reaction may be increased to up to 10% of the reaction volume, but the transformation efficiency may be reduced.

Heat Pulse Duration: Optimal transformation efficiency is observed when cells are heat-pulsed at 42° C for 45-50 seconds. Efficiency decreases sharply when cells are heat-pulsed for <45 seconds or for >60 seconds.

PREPARATION OF MEDIA AND REAGENTS

SOB Medium (per Liter)	SOC Medium (per 100 ml)
20.0 g of tryptone	Note This medium should be prepared immediately before use.
5.0 g of yeast extract	
0.5 g of NaCl	2 ml of filter-sterilized 20% (w/v) glucose or 1 ml of filter-sterilized
Add deionized H_2O to a final volume of 1 liter	2 M glucose
Autoclave	SOB medium (autoclaved) to a final volume of 100 ml
Add 10 ml of filter-sterilized 1 M MgCl ₂ and 10 ml of filter-sterilized	
1 M MgSO ₄ prior to use	
LB Agar (per Liter)	LB–Ampicillin Agar (per Liter)
10 g of NaCl	1 liter of LB agar, autoclaved
10 g of tryptone	Cool to 55°C
5 g of yeast extract	Add 10 ml of 10 mg/ml filter-sterilized ampicillin
20 g of agar	Pour into petri dishes (~25 ml/100-mm plate)
Add deionized H ₂ O to a final volume of 1 liter	
Adjust pH to 7.0 with 5 N NaOH	
Autoclave	

LIMITED PRODUCT WARRANTY

This warranty limits our liability to replacement of this product. No other warranties of any kind, express or implied, including without limitation, implied warranties of merchantability or fitness for a particular purpose, are provided by Stratagene. Stratagene shall have no liability for any direct, indirect, consequential, or incidental damages arising out of the use, the results of use, or the inability to use this product.

ENDNOTES

pBluescript® is a registered trademark of Stratagene in the United States.

Stratagene Technical Services USA/Canada (Toll-free) 800 894 1304 Europe (Toll-free) 00800 7400 7400

Email tech_services@stratagene.com World Wide Web www.stratagene.com